

Assigning Software Keys

The following steps need to be performed:

- Add the new software key to the system
- Assign the Software key to Customers
- Manually and automatically updating the system to include the new Software key

Note: It is very important that these steps be performed accurately. If not, the customer will not be able to access the application until the manual steps are run again or the A02 1065 automatic update resets the settings.

Adding the new software key to the system

Note: This must be done on the traditional menu system.

1. On command line, enter WRKDBF XX0008F.

```
System: SAL                                Work with Database File                                Version: V10.11.04
File: XX0008F      Menu System : S/W Definition File      DD      Window: 1
Library: DANCICTRL  Format: XX0008R      Nbr. Records:    31      Record Length: 60
Member: XX0008F    Type: PF      Size (Bytes):    8,192      Access: *INDEXED  WRKDBF==>

Opt: 2=Change record  3=Copy record  4=Delete record  5=Display record  6=Print record
      ...5...10...15...20...25...30...35...40...45...50...55...60...65...70...75...80...85...90...95...100...105...110...115...120...125
Software
Code      Description
- BUILDERBID  BUILDER BID MANAGER
- CRA         ARMSTRONG CORPORATE RETAIL ACCOUNTS
- DAL-TILE    DAL-TILE ONLY OPTIONS
- DEALER LOC  DEALER LOCATOR
- EDI         ELECTRONIC DATA INTERCHANGE
- FTI-ONLY    FLORIDA TILE ONLY ACCESS
- F24         FLOOR 24
- GOE         DANCIK GUI ORDER ENTRY
- IB          IMAGE BUILDER
- IBC         IMAGE BUILDER CONNECTION (TO FLOOR/24)
- ICS         INTERNET CONNECTIVITY SERVICES
- INSTLLSCHD  INSTALLATION SCHEDULER
- IWMS        INTEGRATED WAREHOUSE MANAGEMENT SYSTEM
- IWMS FLEX   I.W.M.S. - FLEXIBLE ALLOCATION
- IWMSBLITE   IWMS 8 CHARACTER LOCATION WAREHOUSE SCREENS ONLY
F3=Exit  F4=Position  F6=Add record  F11=Headings  F14=Fields  F16=Find  F18=SQL Cmds  F19=Left  F20=Right  F24=More keys +
```

Note: You can also use the DBU XX0008F and/or UPDDTA XX0008F commands.

2. To add a new record press **F6**.

System: SAL Work with Database File Version: V10.11.04

File: XX0008F Menu System : S/W Definition File DD Window: 1

Library: DANCICTRL Format: XX0008R Nbr. Record

Member: XX0008F Type: PF Size (Bytes)

Opt: 2=Change record 3=Copy record 4=Delete rec
5...10...15...20...25...30...35...40...45.

Software

Code	Description
BUILDERBID	BUILDER BID MANAGER
CRA	ARMSTRONG CORPORATE RETAIL ACCOUNTS
DAL-TILE	DAL-TILE ONLY OPTIONS
DEALER LOC	DEALER LOCATOR
EDI	ELECTRONIC DATA INTERCHANGE
FTI-ONLY	FLORIDA TILE ONLY ACCESS
F24	FLOOR 24
GOE	DANCIK GUI ORDER ENTRY
IB	IMAGE BUILDER
IBC	IMAGE BUILDER CONNECTION (TO FLOOR/
ICS	INTERNET CONNECTIVITY SERVICES
INSTLLSCHD	INSTALLATION SCHEDULER
IWMS	INTEGRATED WAREHOUSE MANAGEMENT SYS
IWMS FLEX	I.W.M.S. - FLEXIBLE ALLOCATION
IWMS8LITE	IWMS 8 CHARACTER LOCATION WAREHOUSE SCREENS ONLY

F3=Exit F4=Position F6=Add record F11=Headings F14=Fields F16=Find F18=SQL Cmds F19=Left F20=Right F24=More keys

Add a Database Record

Base PF: XX0008F Library: DANCICTRL Member: XX0008F

Field Name	Field Description	Field Value
X8SOFTWARE	Software Code	
X8DESC	Description	

F3=Exit F10=Allow Lowercase

3. Press to **Enter** to continue. Enter a "Y" to confirm and press **Enter** to continue. Press **F3** to exit.

Assign the Software key to Customers

1. From a command line, issue the command **CALL XX3006C**. The Work w/ Customer Software Setup screen appears.

2/16/07 Dancik International, Ltd. XX3006R

16:27:42 Work w/ Customer Software Setup YB

Type options, press Enter.

2=Change 4=Delete R=Remove System

Software	Software	Software
Opt Code Cust/400	Opt Code Cust/400	Opt Code Cust/400
[] CRA ADC400	[] CRA CAIN400	[] CRA FSI400
[] RDC ADC400	[] RDC CAIN400	[] F24 FSI400
[] CRA ADL400	[] CRA DEXTER	[] ICS FSI400
[] RDC ADL400	[] DEALER LOC DEXTER	[] RDC FSI400
[] CRA BRF400	[] EDI DEXTER	[] ROCS FSI400
[] RDC BRF400	[] IB DEXTER	[] DEALER LOC GESCO400
[] CRA BWG400	[] IBC DEXTER	[] F24 GESCO400
[] F24 BWG400	[] ICS DEXTER	[] ICS GESCO400
[] ICS BWG400	[] RDC DEXTER	[] ROCS GESCO400
[] RDC BWG400	[] ROCS DEXTER	[] ICS IDI400
[] CRA BWL400	[] ICS ECT400	[] ICS IDS400
		More...

F1=Create F7=Exit

If you use option **4** on this screen to delete a software key you are deleting it completely out of the system. This means that every customer who has bought and paid for the application cannot access it. To delete, select the software code and individually clear those systems that no longer use the application. This must also be done on the customer's system to confirm that the customer does not have access to the application.

2. Press **F1** and select the software key you want to assign to a customer.

```

      2/16/07          Dancik International, Ltd.         XX3006RA
     16:44:07        Work w/ Customer Software Setup       YB
-----
Software Code ..... MFGRCVCON                          2=Change

Cust/400    Cust/400    Cust/400    Cust/400    Cust/400    Cust/400
FTRS401     _____  _____  _____  _____  _____
FT400       _____  _____  _____  _____  _____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
_____  
_____
More...

F6=Return   F7=Exit                                     H
```

3. Enter the customers system name.

Manually and automatically updating the system to include the new Software key

Manually

This process must be run on both SAL and the customer's system.

Automatically

Update A02 1065, which is run monthly, updates the customer's systems to the settings on SAL.

