

Dancik Open-WebService Reference

Function ID/Path : /iwms/displayDockDoorSummary

This function retrieves the summarized dock door data showing statuses and counts.

Inputs :

| Variable | Type | Req? | Description |
|-----------|-----------|------|-------------|
| warehouse | string(3) | Y | Warehouse |

Example (XML) :

```
<dancik-api-request>
  <warehouse> XXX </warehouse>
</dancik-api-request>
```

Example (JSON) :

```
{
  "warehouse" : " XXX "
}
```

Outputs :

Layout name : records

| Variable | Type | Description |
|----------------|------|---|
| DockDoorId | | Dock Door Id |
| DockDoorDesc | | Dock Door Description |
| OpenLines | | Open Line Count |
| OpenPrct | | Percentage of Open Lines to Total Lines |
| OpenWeight | | Weight in LBs of Open Lines |
| AdjustedLines | | Adjusted Line Count |
| AdjustedPrct | | Percentage of Adjusted Lines to Total Lines |
| AdjustedWeight | | Weight in LBs of Adjusted Lines |
| PutawayLines | | Putaway Line Count |
| PutawayPrct | | Percentage of Putaway Lines to Total Lines |
| PutawayWeight | | Weight in LBs of Putaway Lines |
| TotalLines | | Total Number of Lines |
| TotalWeight | | Total Weight in LBs of All Lines |

Example (XML) :

```
<dancik-api-response>
  <records>
    <DockDoorId> XXX </DockDoorId>
    <DockDoorDesc> XXX </DockDoorDesc>
    <OpenLines> XXX </OpenLines>
    <OpenPrct > XXX </OpenPrct >
    <OpenWeight > XXX </OpenWeight >
    <AdjustedLines> XXX </AdjustedLines>
    <AdjustedPrct > XXX </AdjustedPrct >
    <AdjustedWeight > XXX </AdjustedWeight >
    <PutawayLines> XXX </PutawayLines>
    <PutawayPrct > XXX </PutawayPrct >
    <PutawayWeight > XXX </PutawayWeight >
    <TotalLines > XXX </TotalLines >
    <TotalWeight > XXX </TotalWeight >
  </records>
</dancik-api-response>
```

Example (JSON) :

```
{
  "records" : {
    "DockDoorId" : " XXX ",
    "DockDoorDesc" : " XXX ",
    "OpenLines" : " XXX ",
    "OpenPrct " : " XXX ",
    "OpenWeight" : " XXX ",
    "AdjustedLines" : " XXX ",
    "AdjustedPrct " : " XXX ",
    "AdjustedWeight" : " XXX ",
    "PutawayLines" : " XXX ",
    "PutawayPrct " : " XXX ",
    "PutawayWeight" : " XXX ",
    "TotalLines" : " XXX ",
    "TotalWeight" : " XXX "
  }
}
```

Dancik Open-WebService Reference

Function ID/Path : /iwms/displayDockDoorSummary

This function retrieves the summarized dock door data showing statuses and counts.

History :

| Date | Description |
|------------|-------------|
| 08/16/2016 | New Call |